

# How to set up PrusaSlicer

This will setup PrusaSlicer for the **Klipper Printer Additions**, and if you like for **Object Exclusion**, too. I made this guide with PrusaSlicer 2.6/2.7.

## Start G-code

- Click **Printer Settings** --> **Custom G-code** section.

## PrusaSlicer V2.5 and higher

- The following text block contains **minimized text lines**, so it has no line breaks on copy & paste, which would later lead to error messages.
- Select** the following **ENTIRE** text block. **Do not copy line-per-line!** Copy & Paste the **entire** text block into the **Machine Start G-code**:

; This is a text block with minimized lines.

;;; KPA Start


M109 S0

M190 S0

;; Pre\_Print\_Procedure  
BED\_TEMP={first\_layer\_bed\_temperature[initial\_extruder]}  
EXTRUDER\_TEMP={first\_layer\_temperature[initial\_extruder]}  
AREA\_START={first\_layer\_print\_min[0]}, {first\_layer\_print\_min[1]}  
AREA\_END={first\_layer\_print\_max[0]}, {first\_layer\_print\_max[1]}  
LAYER\_C={total\_layer\_count} LAYER\_H={layer\_height}  
FILAMENT\_TYPE={filament\_type} NOZ\_DIA={nozzle\_diameter[0]}  
M140 S{first\_layer\_bed\_temperature[initial\_extruder]} ; Let a Power failure Resume feature pickup the temperature.  
M104 S{first\_layer\_temperature[initial\_extruder]} ; Let a Power failure Resume feature pickup the temperature.

;;; KPA End

- You don't need anything else in your **Start G-code**. If you have g-code commands in there, comment them out, or delete them.



- You don't need anything else in your start-g-code. If you have g-code commands in there, comment them out, or delete them.

## PrusaSlicer before version 2.5 (untested)

- The following text block contains **minimized text lines**, so it has no line breaks on copy & paste, which would later lead to error messages.
- **Select** the following **ENTIRE** text block. **Do not copy line-per-line!** Copy & Paste the **entire** text block into the **Machine start G-code**:

; KPA Start

M109 S0

M190 S0

;Pre\_Print\_Procedure BED\_TEMP={first\_layer\_bed\_temperature} EXTRUDER\_TEMP={first\_layer\_temperature[initial\_extruder] + extruder\_temperature\_offset[initial\_extruder]} AREA\_START={first\_layer\_print\_min[0]},first\_layer\_print\_max[1]} AREA\_END={first\_layer\_print\_max[0]},first\_layer\_print\_max[1]} LAYER\_C={total\_layer\_count} LAYER\_H={layer\_height} FILA\_TYPE={filament\_type[0]} NOZ\_DIA={nozzle\_diameter[0]}

M140 S{first\_layer\_bed\_temperature} ; Let a Power failure Resume feature pickup the temperature.

M104 S{first\_layer\_temperature[initial\_extruder] + extruder\_temperature\_offset[initial\_extruder]} ; Let a Power failure Resume feature pickup the temperature.

; KPA End

## End G-code

- For the **End G-code** section, copy & paste this text block:


; KPA Start

\_End\_Print

; KPA End


- This is a macro of the Printer Additions which cleans up state, lifts up the extruder a bit higher, retracts a bit more, and turns off the heaters, motors, fans.

- You don't need anything else in your **Machine end G-Code**. If you have g-code commands in there, comment them out, or delete them.




## Slicer Modes

- In the **Print Settings**, under the **General**-section, set the **g-code flavor** to "Klipper":




- Also in the **General**-section, turn ON "Use relative E distances". Otherwise your extruder will spin like crazy.



## Object Exclusion

Open **Print Settings**, --> "**Output options**" and set "**Label objects**" to "**Firmware-specific**". In older releases of PrusaSlicer there's just a checkbox to tick.



## Support

If my work supports you, please support me too:

- PayPal: <https://www.paypal.com/paypalme/Morgennebel/>

When you buy something, please use my Referral-Link, at no additional cost:

- AliExpress: [https://s.click.aliexpress.com/e/\\_De0Vu1h](https://s.click.aliexpress.com/e/_De0Vu1h)
- Amazon: <https://amzn.to/3L35OX2>

Thank you!

Christian 😊